



# AromaController

## Manual



Windows 8  
Or later








Mac OS X



Ubuntu 16.04 or  
later  
& Debian

— Ver.2.0.0 —

# AromaController Manual - Table of Contents

-  [Download](#)
-  [Installation](#)
-  [Connection with the Aroma Shooter](#)
-  [Application and user guide](#)
-  [Application settings](#)




Click on each part to jump to the content page.

# Download the application

① Open the **AromaController** page from the Aromajoin's Homepage.


<https://aromajoin.com/en/software/apps/aroma-controller>

News Products ▾ Apps ▾ Aromajoin ▾ Careers Support Blog 🔍



## Application

Homepage / Application



## AromaController

AromaController application allow you to connect the Aroma Shooter to your devices (PC, smartphone, Tablet) and provide you a very simple way to control scents.

### Features

- Desktop AromaController can be used with Aroma Shooter USB type
- Android and iOS AromaController can be use with Aroma Shooter Bluetooth type
- Very easy to use. Connect devices and diffuse scent
- Application can be customize

**Warning:** In case of iOS devices, only Aroma Shooter Bluetooth type can be supported.

Android iOS Windows MacOS X Ubuntu

### Prerequisites

### Documents




# Download the application

- ② 1. Click on the button of your OS  
2. Click on the download link and the download will begin

**\*Before starting to download, please check your OS compatibility.**



Windows 8  
or later



Mac OS X



Ubuntu 16.04 or later  
& Debian

Android

iOS

Windows

MacOS X


Ubuntu



## Prerequisites

- Aroma Shooter USB
- Windows 8+

## Download (FREE)



AromaController Zip file

# Installation

① Unzip the downloaded file and open the folder.



② The folder will vary depending on the OS version.



## For Windows 8 or later

1. Double click on **CDM21228\_Setup.exe** to install the driver. **【Required】**
2. Double click on **AromaController-2.0.0-win.exe** to install the AromaController application.



## For Mac OSX

1. Double click on **FTDIUSBSerialDriver\_v2\_4\_2.dmg** to install the driver. **【Required】**
2. Double click on **AromaController-2.0.0-mac.dmg** to install the AromaController application.




## For Ubuntu 16.04 or later/ Debian

1. Double click on **AromaController-2.0.0-amd64.deb** to install the AromaController application.



When installation process is completed,  
a shortcut will be create on your desktop.


# Connection with the Aroma Shooter



Connect the USB side (bigger one) of the cable to PC, and the micro USB (smaller one) to the Aroma Shooter.

❌ Please pay attention to the connection direction for micro USB (smaller one).  
It may cause damage.

# Application and user guide



Double-click on the icon to launch the application.

**✗ Before open the application, make sure that the Aroma Shooter is connected.**

**If you open the application before connecting the Aroma Shooter, it will be not recognized.**

# Application and user guide

Click button to diffuse Aroma



✂ If the Aroma Shooter is not recognized even after rebooting.  
Please uninstall the application and try installation again.

© 2019 AROMAJOIN CORPORATION

Settings

Click on the settings  
button to change  
parameters



# Application settings

Connected devices

ASN1UA0150

## Aroma Cartridge

Cartridge 1	Cartridge 2
Aroma 1	Aroma 2
Cartridge 3	Cartridge 4
Aroma 3	Aroma 4
Cartridge 5	Cartridge 6
Aroma 5	Aroma 6

## Basic settings

English

Background

Choose an image [Browse](#)

Diffuse duration (s)

1

Shape of buttons

Circle

App Theme

Dark

[Reset settings](#) [Contact Us](#)

【 Connected devices 】 ...List of all connected devices

【 Aroma Cartridge 】 ...Settings for each cartridge (Name, Picture)

【 Basic settings 】 ...Language, Background, Duration, Shape, Theme

# Application settings

## Device Name

Connected devices

ASN1UA0150

Name of the connected device (Aroma Shooter)

Connected devices

No connection

※If [No connection] , please check the device connection and restart the application.



# Application settings


## Device Name

### Example with several connected devices



List of the connected devices

※ All connected Aromashooter will be used at the same time. Connected devices can not be used with different settings.



※ To control only one device while connecting multiple Aroma Shooters, select the device in the list.

# Application settings

## Aroma Cartridge Settings

**Aroma Cartridge**


Cartridge 1	Cartridge 2
Aroma 1	Aroma 2
Cartridge 3	Cartridge 4
Aroma 3	Aroma 4
Cartridge 5	Cartridge 6
Aroma 5	Aroma 6

Select and click and the cartridge you want to set. The setting window will appear

**Update cartridge** [X]

Cartridge name  
Aroma 6 ✓

Button image  
Choose an image [Browse]



[OK]

**Cartridge Name**

**Cartridge Picture** ※2MB Max

When all your settings are done, click [OK] to save it.

# Application settings

## Basic settings

### <Language>

Select the Application language. [日本語(Japanese)] or [English]

#### Basic settings

日本語

日本語



English



# Application settings

## Basic settings

### < Background >



※Picture size: MAX 2 MB

# Application settings

## Basic settings

< Diffuse duration (Sec) >

Diffuse duration (s)

2

噴射時間 (秒)

1

0

1

2

3

4

5

6

7

8

9

10


※ The Diffuse time can be set between 0 and 10 sec

The image shows a screenshot of a device's application settings. At the top, there's a title 'Application settings' in green. Below it, 'Basic settings' is highlighted with a green bar. Under 'Basic settings', there's a section for 'Diffuse duration (Sec)' with left and right arrow icons. The main part of the screen shows a dark grey bar with the text 'Diffuse duration (s)' and a slider set to '2'. A hand icon is shown adjusting the slider. Below this, there's a dropdown menu titled '噴射時間 (秒)' (Spray time in seconds). The dropdown is open, showing a list of numbers from 0 to 10. The number '1' is highlighted in blue, and a hand icon is shown selecting it. A green arrow points from the '2' on the slider to the '1' in the dropdown. At the bottom right, there's a note: '※ The Diffuse time can be set between 0 and 10 sec'.


# Application settings

## Basic settings


### <Shape of buttons>



※ The shape can be set between [Circle] and [Square]



Circle




Square




# Application settings

## Basic settings

### <App Theme>



※ The theme can be set between [Light] and [Dark]



Dark




Light

# Application settings

## Basic settings

### <Others>

[Reset settings] and [Contact Us]



※ Click [OK] to restore default setting.

All picture and name will be erase.


※ Contact information

To go back to the settings screen, click [Settings >](#)

# Application settings

## Basic settings

✂ When all your settings are done, click **Home >** to go back to the main screen



# Application settings



✂ This is an example of customize settings

# Thank you



[contact@aromajoin.com](mailto:contact@aromajoin.com)

<https://aromajoin.com>